


Construction of Appliqué Unit

Cut out the centers of Templates A and C, leaving only the seam allowance.




Lay Template A on top of the previously cut pieces of Fabric 7. Using a marking pencil, draw the sewing line on the *right side* of the fabric as illustrated.




Lay Template C on top of the previously cut pieces of Fabric 10. Using a marking pencil, draw the sewing line on the *right side* of the fabric as illustrated.




Cut out the center of Template E. Lay Template E on top of the previously cut pieces of Fabric 14. Using a marking pencil, draw the sewing line on the *right side* of the fabric as illustrated.




Sew a Fabric 10 (Template C) to a Fabric 6 (Template D) to make **Section 1**. Make 8.




Sew a Fabric 10 (Template C) to a Fabric 6 (Template B) to make **Section 2**. Make 32.




Sew a Fabric 7 (Template A) to a **Section 2** to make **Section 3**. Sew to the dot (seam allowance). Do not sew past dot. Make 32.




Sew a Fabric 7 (Template A) to a Fabric 6 (Template DR) to make **Section 4**. Sew to dot. Make 8.




Sew the **Sections 1, 3, and 4** together as illustrated below to form the top section of the appliqué unit. Do not stitch through dots. Make 8.




Turn under the seam allowance to the marked line on the curved edge of Fabric 14 (Template E). Baste close to edge with a running stitch. Make 8.



Turn under the seam allowance to the marked line on the scalloped edges of Fabric 7 (Template A).



Line up the top edge of Fabric 14 to the marked line on Fabric 10 (Template C). Appliqué Fabric 14 (Template E) to the top section of appliqué unit. Remove basting stitches from Fabric 14.



Cutting Corner Squares and Set-in Triangles

Cut 2 - 17 1/2" wide strips of Fabric 18.


Cut into 4 - 17 1/2" squares.

Cut 1 - 25 1/4" square of Fabric 18. Cut on both diagonals.




Appliqué Unit to Corner Square and Set-in Triangles

Place an appliqué unit on the corner of the 17 1/2" square of Fabric 18 (Black Millennium Marble). Baste the sides of the appliqué unit 1/8" away from the sides of the 17 1/2" square as illustrated.



Appliqué the scalloped edge of Fabric 7 to the 17 1/2" square. Remove the basting from the scalloped edge. Do not remove the basting that holds the appliqué unit to the corner square. Repeat the process on the remaining 3 corner squares.

Place an appliqué unit on the 90° corner of the Fabric 18 set-in triangle. Baste the sides of the appliqué unit 1/8" away from the sides of the set-in triangle as illustrated.



Appliqué the scalloped edge of Fabric 7 to the set-in triangle. Remove the basting from the scalloped edge. Do not remove the basting that holds the appliqué unit to the set-in triangle. Repeat the process on the remaining 3 set-in triangles.